

OSCE Code 7457-350 Laboratory Diagnostics 07 (Ear swab) for Unit 309

This station covers the following RCVS Day One Skills: 1.1, 2.7, 3.3, 3.6, 5.2, 5.9, 8.3

This OSCE will be used to assess the awards indicated

Award	Award Reference	Pathway
7457 – Level 3 Diploma in Veterinary Nursing	600/6052/6	Small Animal
7457 – Level 3 Diploma in Veterinary Nursing	600/6052/9	Equine

Scenario

The veterinary surgeon has requested that an aural swab is taken for bacterial culture by an external laboratory.

Using the equipment provided, take an aseptic sample from the x ear of this patient.

Package the sample to meet UN packaging instruction P650, ready for dispatch to the external laboratory.

This will be sent via the postal service.

Please note: You have already washed your hands.

You	You will be expected to:		
1.	Select charcoal swab		
2.	Ask for assistance and give instructions for the patient to be restrained		
3.	Select and wear gloves prior to commencing the procedure		
4.	Using the swab, collect sample from the ear without contamination		
5.	Collect sufficient sample for analysis by gently rotating swab to cover all surfaces		
6.	Patient handled and sample collected without causing trauma to the ear		
7.	Replace swab into the cover tube and secure		
8.	Remove gloves and dispose of correctly		
9.	Label swab with the location sample is being collected from (e.g. left ear)		
10.	Label swab with the animal's name/ID, owner's name and the date		
11.	Sample correctly collected and labelled using a safe, effective and aseptic technique		
12.	Insert client's name on laboratory form		
13.	Insert animal's details on laboratory form		
14.	Sample type submitted on laboratory form		
15.	Insert test required on laboratory form		
16.	Wrap swab in absorbent material		
17.	Wrap swab in bubble wrap		
18.	Place swab in polythene bag		
19.	Remove air from polythene bag and seal		
20.	Place laboratory form in polythene bag (separated from sample)		
21.	Place form and sample into outer packaging		
22.	Secure outer packaging		
23.	Place completed package in post tray – ready for submission		
24.	Sample packed to meet United Nations packaging instructions P650		
25.	Contaminated gloves not worn during completion of steps 9-23		